


[Click here to see the interactive prototype](#)

- 1 MODAL NAVIGATION DRAWER**
 - Fixed position on page
 - Appears as an overlay on top of the page content
 - 2 states: expanded and collapsed states visible to the user
 - **When expanded**, all content on page is in default state
- 2 MUSIC THUMBNAIL CARDS BLOCK**
 - Block vertically scrollable on page
 - 3 states: default, focused, preview
 - **All cards in default state**, when Modal navigation drawer(2) is expanded
 - **All cards in default state**, when focus is on Sorting/Filter block(3)
 - **All cards in default state**, when focus is on Profile block(4)
- 3 SORTING/FILTER BLOCK**
 - Block vertically scrollable on page **when expandable filter panels(3b) are expanded**
 - 3 component types: Dropdown sort list(3a), Expandable filter panels(3b) and Clear filters button(3c)
 - **When Clear filters button(3c) is pressed**, Sorting/filter block(3) change to default state (Dropdown sort list(3a) keeps the last sorting option selected by user)
- 4 PROFILE BLOCK**
 - Fixed position on page
 - 2 states: default, focused
 - **When pressed**: brings users to profile page






REFERENCE DIMENSIONS FOR 1920 X 1080 PX RESOLUTION SCREEN



[Click here to see the interactive prototype](#)

- 1 NAVIGATION TABS**
 - 3 states on Expanded modal navigation drawer(2): Default(1a), Active(1b), Focused(1c)
 - 2 states on Collapsed Modal navigation drawer(3): Default(1d), Active(1e)
- 1a DEFAULT STATE TABS (EXPANDED AND COLLAPSED)**
 - Font size: min 18 px
 - 36 px (on 1920 x 1080 px resolution screen)
 - Font color: Needs to contrast on background (Avoid saturated color or pure white)
- 1b ACTIVE STATE TABS (EXPANDED AND COLLAPSED)**
 - Font size: min 18 px
 - 36 px (on 1920 x 1080 px resolution screen)
 - Font color: Needs to contrast on background (Avoid saturated colors or pure white)
 - Background color: Avoid saturated colors

- 1c FOCUSED STATE TABS (ONLY EXPANDED)**
 - Font size: min 18 px
 - 36 px (on 1920 x 1080 px resolution screen)
 - Font color: Needs to contrast on background (Avoid saturated colors or pure black)
 - Background color: Needs to be lighter than Active state, Avoid saturated colors
- **When pressed**, the focused tab becomes the Active tab and the Modal navigation drawer collapses(3)





- 2 EXPANDED MODAL NAVIGATION DRAWER**
 - Fixed position on page
 - Appears as an overlay on top of the page content
 - Background color: Same or close to background color (avoid pure black)
 - **When expanded**, all content on page is in default state
 - **After/on expansion**, the current Active tab becomes the default Focused tab
 - **When a tab is pressed in the expanded modal navigation drawer(2)**, the navigation drawer changes to collapsed state(3), and the selected tab changes to Active state

- MOVE UP**
 - Goes to the tab above
 - **if on the FIRST tab**: Goes to the last tab of the navigation drawer
- MOVE DOWN**
 - Goes to the tab below
 - **if on the LAST tab**: Goes to the first tab of the navigation drawer

- MOVE RIGHT**
 - **Collapses to Collapsed Modal Navigation drawer state(3)**
 - Current page stays the same
 - The Music thumbnail card that was in Focused state before opening the navigation, becomes focused again
- MOVE LEFT**
 - **Collapses to Collapsed Modal Navigation drawer state(3)**
 - Active page stays the same
 - The Music thumbnail card that was in Focused state before opening the navigation, becomes focused again

- CONFIRM BUTTON**
 - **Collapses to Collapsed Modal Navigation drawer state(3)**
 - Active page changes
 - Content on page changes to related selected tab
- BACK BUTTON**
 - **Collapses to Collapsed Modal Navigation drawer state(3)**
 - Active page stays the same
 - The Music thumbnail card that was in Focused state before opening the navigation, becomes focused again





- 3 COLLAPSED MODAL NAVIGATION DRAWER**
 - Fixed position on page
 - Inactive on page
 - Background color: Same or close to background color (avoid pure black)
 - **When collapsed**, No tab is in focused state
 - **When collapsing**, focused state on tab disappears

- MOVE UP**
 - Goes to the music thumbnail card above
 - **if on the FIRST music thumbnail card of the column**: Does nothing
- MOVE DOWN**
 - Goes to the music thumbnail card below
 - **if on the LAST music thumbnail card of the column**: Does nothing

- MOVE RIGHT**
 - Goes to the next music thumbnail card in the row
 - Current page stays the same
 - The Music thumbnail card that was in Focused state before opening the navigation, becomes focused again
- MOVE LEFT**
 - **Expands the Modal Navigation drawer(2)**
 - The current active tab on Navigation drawer changes to focused state
 - The Music thumbnail card that was in Focused state changes to default state

- CONFIRM BUTTON**
 - Goes to the next page on customer's journey
- BACK BUTTON**
 - **Expands the Modal Navigation drawer(2)**
 - The current active tab on Navigation drawer changes to focused state
 - The Music thumbnail card that was in Focused state changes to default state



[Click here to see the interactive prototype](#)

1 MUSIC THUMBNAIL CARDS
- 3 states: Default(1a), Focused(1b), Focused-Preview(1c)



- 1a MUSIC THUMBNAIL DEFAULT STATE**
- Displays a fix image of the choreography dancers, the Music title, the Difficulty level and the current player Score (stars)
 - Dark gradient overlay on top of image: to make text more readable
 - Music title font size: Bold - min 16 px 32 px (on 1920 x 1080 px resolution screen)
 - Music title font color: Needs to contrast on background (avoid saturated color or pure white)
 - Difficulty level font size: min 12 px 24 px (on 1920 x 1080 px resolution screen)
 - Difficulty level font color: Slightly darker than Music title font color. Needs to contrast on background (avoid saturated color or pure white)

- 1b MUSIC THUMBNAIL FOCUSED STATE**
- Displays the image without dark gradient overlay on top of the image.
 - Needs a visual effect to visually detach the card from the default/inactive other cards.
 - **After 300ms on focused state**, the card state changes to focused-preview State

- 1c MUSIC THUMBNAIL FOCUSED-PREVIEW STATE**
- Plays instantly 10-second-choreography preview video (chorus choreography) with sound (chorus)
 - Displays the Music title and the singer name
 - Displays the Difficulty level and the current player Score (stars)
 - Music title font size: Bold - min 16 px 32 px (on 1920 x 1080 px resolution screen)
 - Music title font color: Needs to contrast on background (avoid saturated color or pure white)

- 1c MUSIC THUMBNAIL FOCUSED-PREVIEW STATE (SUITE)**
- Singer name and difficulty level font size: min 12 px 24 px (on 1920 x 1080 px resolution screen)
 - Singer name and difficulty level font color: Slightly darker than Music title font color. Needs to contrast on background (avoid saturated color or pure white)

- Card background: same or similar color to background color
- Needs a visual effect to visually detach the card from the default/inactive other cards.



- 2 MUSIC THUMBNAIL CARD BLOCK**
- Block vertically scrollable on page
 - Vertical scroll stars when reaching the 3rd row
 - Vertical scroll width: 52 px (on 1920 x 1080 px resolution screen)
 - Scroll width needs to be less than the size of the card
 - **(2b)** Last row on the page needs to be partially visible to indicate the user that the content is scrollable
 - **Default page opening:** focus on the 1st card top left
 - **All cards in default state**, when Modal navigation drawer is expanded
 - **All cards in default state**, when focus is on Sorting/Filter block
 - **All cards in default state**, when focus is on Profile block

- MOVE UP**
- Goes to the **card above in the same column**
 - if on the **FIRST** row: Does nothing



- MOVE RIGHT**
- **Goes to the next card** on the right in the same row
 - if on the **LAST** column: focus on dropdown sort list and all cards change to default state

- CONFIRM BUTTON**
- Goes to the next page on customer's journey

- MOVE DOWN**
- Goes to the **card below in the same column**
 - if on the **LAST** row: Does nothing


- MOVE LEFT**
- **Goes to the previous card** on the left in the same row
 - if on the **First** column: Opens Modal Navigation drawer and all cards change to default state

- BACK BUTTON**
- **Expands the Modal Navigation drawer**
 - The current active tab on Navigation drawer changes to focused state
 - The card that was in Focused state changes to default state




[Click here to see the interactive prototype](#)


- 1 DROPPDOWN SORT LIST**
 - 2 states: Expanded or Collapsed
 - In collapsed state, only the dropdown sort list button(1a) is visible
 - When collapsed**, if the dropdown sort list button(1a) is pressed: dropdown expands
 - When expanded**, if the dropdown sort list button(1a) is pressed: dropdown collapses
 - When dropdown expands**, the main button stays in focus state
 - Remembers the last sorting options selected by the user and sets it as the **default sorting** for the next time the user plays
 - Dropdown opens/expands over the content below on main interface
- 1a DROPPDOWN SORT LIST BUTTON**
 - Font size: min 14 px
 - 28 px (on 1920 x 1080 px resolution screen)
 - Font & Background color: Same rules as Navigator tabs
 - Make sure the sort list button is **discernable from buttons below** (expandable filter panel buttons)
 - 4 states: Default, Focused-Collapsed, Focused-Expanded, Active
 - The button is in Active or Focused-Expanded state as long as the dropdown is expanded
 - Cannot be in Default or Focused-Collapsed state when the dropdown is expanded
 - The button is in **focused-expanded state** after the dropdown just expanded
 - The button is in **focused-collapsed state** after the dropdown just collapsed
- 1b DROPPDOWN SORT LIST SORTING OPTIONS**
 - Font size: min 14 px
 - 28 px (on 1920 x 1080 px resolution screen)
 - Font & Background color: Same rules as Navigator tabs
 - 2 states: Default and Focused
 - When a sorting option is selected**: the dropdown collapses, the selected sorting option is populated on the main button **and** the displayed music thumbnails cards on page change accordingly to the selected sorting option
 - The last selected sorting option selected by the user becomes the **default sorting option**, until the user selects another sorting option
- 1b DROPPDOWN SORT LIST SORTING OPTIONS (SUITE)**
 - Font size: min 14 px
 - 28 px (on 1920 x 1080 px resolution screen)
 - Font & Background color: Same rules as Navigator tabs
 - A-Z sorting option**: sorts Music cards on page by alphabetic order
 - Z-A sorting option**: sorts Music cards on page by reverse alphabetic order
 - Favourites sorting option**: sorts Music cards on page by the most Music played by the user
 - Easy first sorting option**: sorts Music cards on page by the Easiest to the most difficult
 - Recent sorting option**: sorts Music cards on page by the most recently added to the least recent




- 1 DROPPDOWN SORT LIST**
 - The dropdown sort list button is in **focused-expanded state** when the dropdown just expanded
 - The dropdown sort list button is in **focused state** when the dropdown just collapsed
 - Dropdown opens/expands over the content below on main interface
 - Dropdown is **collapsed and the dropdown button is in default mode** when the focus is on the Music thumbnail cards OR on the filter panel button OR on the Profile pictures OR if the modal navigator is opened
- MOVE UP**
 - Goes to the **sorting option above**
 - if **FIRST** option in the dropdown list: goes to the dropdown Button
 - if **BUTTON**: goes to the **LAST** option in the dropdown list
 - if collapsed: Goes to the last selected Music card
- MOVE DOWN**
 - Goes to the **sorting option below**
 - if **LAST** option in the dropdown list: goes to the dropdown Button
 - if **BUTTON**: goes to the first option of the dropdown list
 - if dropdown is collapsed: goes to the filter panel button below
- MOVE RIGHT**
 - Goes to the profile picture
 - Dropdown **sort list collapses**
 - Dropdown **button is in default state**
 - No sorting changes**
- MOVE LEFT**
 - Goes to the last selected Music card
 - Dropdown **sort list collapses**
 - Dropdown **button is in default state**
 - No sorting changes**
- CONFIRM BUTTON**
 - if dropdown is **EXPANDED**: dropdown collapses and dropdown button changes to focused state
 - if dropdown is **COLLAPSED**: dropdown expands and dropdown button changes to focused-expanded state
- BACK BUTTON**
 - if dropdown is **EXPANDED**: dropdown collapses and dropdown button changes to focused state
 - if dropdown is **COLLAPSED**: Goes to the last selected Music card



- 2 EXPANDABLE FILTER PANELS**
 - 2 states: Expanded or Collapsed
 - In collapsed state, only the filter panel button(3a) is visible
 - When collapsed**, if the filter panel button(3a) is pressed: filter panel expands
 - When expanded**, if the filter panel button(3a) is pressed: filter panel collapses
 - When filter panel expands**, the filter panel button stays in focus state
 - Stays in **expandable state** when inner filter panel boxes are checked
 - When expanded**, the standard filter panel pushes the block content below making space for the expanded version of the filter panel
- 2a FILTER PANEL BUTTON**
 - Font size: min 14 px
 - 28 px (on 1920 x 1080 px resolution screen)
 - Font & Background color: Same rules as Navigator tabs
 - Make sure the filter panel button is discernable (visually different) from the sort list button above
 - 4 states: Default, Focused-Collapsed, Focused-Expanded, Active-Expanded
 - The button is in **Active or Focused-Expandable state** as long as the dropdown is expanded
 - The button stays in **active-Expanded state** if at least ONE inner filter panel box is checked
 - Cannot be in **Default or Focused-Collapsed state** when the panel is expanded
 - The button is in **focused-expanded state** after the dropdown just expanded
 - The button is in **focused-collapsed state** after the dropdown just collapsed
- 2b FILTER PANEL BOXES**
 - Font size: min 14 px
 - 28 px (on 1920 x 1080 px resolution screen)
 - Font & Background color: Same rules as Navigator tabs
 - 4 states: Default-Unchecked, Focused-Unchecked state, Checked state, Focused checked state
 - When a filter panel box is checked**: the displayed music thumbnails cards on page change accordingly to the selected filter
 - Checked filter boxes **remain checked** until the user leaves the game OR unchecked filter boxes



- 3 CLEAR FILTER BUTTON**
 - Font size: min 14 px
 - 28 px (on 1920 x 1080 px resolution screen)
 - 3 states: Disabled, Enabled, Focused
 - In **Disabled state** as long as no panel filter box is checked
 - Changes to Enabled state** when a filter box is checked
 - When pressed**, all selected panel filter box changes to Default-Unchecked state AND All Expandable filter panels collapse
 - Changes to disabled state** when pressed



- 2 EXPANDABLE FILTER PANEL**
 - When filter panel expands**, the filter panel button stays in focus state
 - Stays in **expandable state** when inner filter panel boxes are checked
 - When expanded**, the standard filter panel pushes the block content below making space for the expanded version of the filter panel
- MOVE UP**
 - Goes to the **filter panel box above**
 - if **FIRST** panel box in the filter panel: goes to the filter panel Button
 - if **BUTTON**, and no inner filter panel box is checked: panel collapses
 - if **BUTTON**, and at least one filter panel box is checked: Goes to the filter panel above
- MOVE DOWN**
 - Goes to the **filter panel box below**
 - if **LAST** panel box in the filter panel: goes to the **next panel Button below**
- MOVE RIGHT**
 - Goes to the profile picture
 - no inner filter panel box** is checked: filter panel collapses
 - if at least **one filter panel box is checked**: filter panel remains expanded
- MOVE LEFT**
 - Goes to the last selected Music card
 - no inner filter panel box** is checked: filter panel collapses
 - if at least **one filter panel box is checked**: filter panel remains expanded
- CONFIRM BUTTON**
 - if **BUTTON** and **no inner filter panel box** is checked: filter panel collapses
 - if **BUTTON** and at least **one filter panel box is checked**: filter panel collapses AND panel button changes to Active state
 - if on unchecked filter panel box **checks the box**
 - if on checked filter panel box **unchecks the box**
- BACK BUTTON**
 - if **no inner filter panel box** is checked: filter panel collapses
 - if at least **one filter panel box is checked**: filter panel collapses AND panel button changes to Active state
 - if on **BUTTON**: Goes to the last selected Music card

